


## [Windows/MAC] CaptureShare Software Release Note – February 1, 2021

<b>VERSION</b>	V1.3.2043.0
<b>HARDWARE COMPATIBILITY</b>	The following product models are supported by CaptureShare. DocCam: U50/U70/U70+/F17-8M/F50-8M/M17-13M/M15-13M/M11-8M/M90UHD/M15W/M70W Tracking cameras: TR333/TR313/TR311/TR310 (TR models Firmware V21 or later) PTZ cameras: PTZ310/PTZ310W/PTZ310N/PTZ330/PTZ330W/PTZ330N (PTZ models V66 or later)
<b>OPERATING DEVICES / SYSTEMS</b>	<ul style="list-style-type: none"> <li>Win OS 7, Win OS 10</li> <li>Mac 10.14 Mac 10.15</li> </ul>

<b>V1.3.2037.0</b>  <b>Release date:</b> <b>November 06, 2020</b>	<b><u>WHAT'S NEW</u></b> <ul style="list-style-type: none"> <li>- Supports AVer DL30 camera (pre-release).</li> <li>- Supports AVer PTZ cameras.</li> <li>- Supports new functions: Sleep Mode/Profile in settings for DL30 (pre-release).</li> <li>- Displays network &amp; device information while connecting the DL30 (pre-release) via USB cable.</li> </ul> <p>*IP Address/ Serial number / Mac address / FW version</p>
	<b><u>BUG FIXED</u></b> <ul style="list-style-type: none"> <li>- Zoom in/out setting should be reset to default value after clicking home button.</li> <li>- Crash happens if user connects two tracking cams at the same time. – Random issue.</li> <li>- Firmware update function should be disable for some models which cannot support firmware upgrade function. [MAC Only]</li> </ul>
	<b><u>KNOWN ISSUES (Win/MAC)</u></b> <ul style="list-style-type: none"> <li>• UVC streaming display isn't workable with &lt;NDI/Streaming only mode&gt;, but users still can select it in the list. A fix is being released for next release. Workaround: Please change the camera mode to "USB only".</li> <li>• Camera 4K resolution can only be selected in USB only mode. <ul style="list-style-type: none"> <li>○ Workaround: Switch mode to "USB only" mode in the web setting.</li> </ul> </li> <li>• PTZ/TR/DL camera models don't have the brightness settings. It cannot be used in some modes and need adjust it in web settings. Working on a fix for next release.</li> <li>• Tracking sensitivity cannot be used in Zone mode.</li> </ul>

<b>VERSION</b>	V1.3.2037.0
<b>HARDWARE COMPATIBILITY</b>	The following product models are supported by CaptureShare. DocCam: U50/U70/U70+/F17-8M/F50-8M/M17-13M/M15-13M/M11-8M/M90UHD/M15W/M70W Tracking cameras: TR333/TR313/TR311/TR310 (TR models Firmware V21 or later)

<b>OPERATING DEVICES / SYSTEMS</b>	<ul style="list-style-type: none"> <li>• Win OS 7, Win OS 10</li> <li>• Mac 10.14 Mac 10.15</li> </ul>
------------------------------------	--

<p><b>V1.3.2037.0</b></p> <p><b>Release date:</b> <b>November 06, 2020</b></p>	<p><b><u>WHAT'S NEW</u></b></p> <ul style="list-style-type: none"> <li>• Supports AVer tracking camera. (TR models)</li> <li>• Supports camera tracking control, and preset settings via UVC. (TR models)</li> <li>• Supports CaptureShare functions (Recording/Streaming/Capture) for TR models.</li> <li>• To access the Camera control tool for PTZ camera control, navigate to the “AVer Information Inc” folder and select the “AVerCamera Setting Tool”.</li> </ul>  <p><b><u>BUG FIXED</u></b></p> <p>N/A (First release version for AVer TR models)</p> <p><b><u>KNOWN ISSUES (Win/MAC)</u></b></p> <ul style="list-style-type: none"> <li>• UVC streaming display isn't workable with &lt;NDI/Streaming only mode&gt;, but users still can select it in the list. A fix is being released for next release. Workaround: Please change the camera mode to “USB only”.</li> <li>• Camera 4K resolution can only be selected in USB only mode. <ul style="list-style-type: none"> <li>○ Workaround: Switch mode to “USB only” mode in the web setting.</li> </ul> </li> <li>• PTZ/TR camera models don't have the brightness settings. It cannot be used in some modes and need adjust it in web settings. Working on a fix for next release.</li> <li>• Crash happens if user connects two tracking cams at the same time. – Random issue. Working on a fix for next release.</li> </ul> <p><b><u>KNOWN ISSUES (MAC Only)</u></b></p> <ul style="list-style-type: none"> <li>• 424x240 resolution cannot be displayed with broken images. Working on a fix for next release.</li> </ul>
--	--